



***Standards for Technology in Automotive Retail***

**Implementation Guidelines  
Show Parts Master  
Repository Version Rev4.5.4**



## Table of Contents

<a href="#">Overview</a>	1
<a href="#">Schema Field Usage</a>	1
<a href="#">Business Scenario</a>	1
<a href="#">Relationship Diagram</a>	3
<a href="#">Schema Document Properties</a>	4
<a href="#">Components and Data Types</a>	5
<a href="#">Amount</a>	5
<a href="#">ApplicationArea</a>	5
<a href="#">BusinessObjectDocument</a>	7
<a href="#">ConfirmableVerb</a>	8
<a href="#">Description</a>	9
<a href="#">Destination</a>	9
<a href="#">DocumentId</a>	11
<a href="#">HeaderBase</a>	11
<a href="#">Id</a>	12
<a href="#">ItemAmount</a>	12
<a href="#">ItemId</a>	13
<a href="#">ItemIdDescription</a>	13
<a href="#">ItemQuantity</a>	13
<a href="#">LocationId</a>	14
<a href="#">NonTaxableAmount</a>	14
<a href="#">PartCoreDetail</a>	15
<a href="#">PartManufacturer</a>	15
<a href="#">PartMaster</a>	16
<a href="#">PartMasterHeader</a>	16
<a href="#">PartMasterLine</a>	17
<a href="#">PartMasterPricing</a>	18
<a href="#">PartsBase</a>	19
<a href="#">PartSupersedingGroup</a>	20
<a href="#">PartyId</a>	20
<a href="#">Quantity</a>	21
<a href="#">QuantityDiscounts</a>	21

<a href="#">ResponseVerb</a>	22
<a href="#">SecondaryDealerNumber</a>	22
<a href="#">Sender</a>	23
<a href="#">SenderBase</a>	26
<a href="#">ServiceId</a>	27
<a href="#">Show</a>	27
<a href="#">ShowPartsMaster</a>	28
<a href="#">ShowPartsMasterDataArea</a>	29
<a href="#">Signature</a>	30
<a href="#">SupersedingItemDescription</a>	31
<a href="#">SupersedingPartDetail</a>	31
<a href="#">SupersedingPartGroup</a>	32
<a href="#">SupersedingPartNumber</a>	33
<a href="#">SupersedingPartNumberUID</a>	33
<a href="#">SupplierItemId</a>	33
<a href="#">TaxableAmount</a>	34
<a href="#">TopSeller</a>	34
<a href="#">TotalAmount</a>	35
<a href="#">UnitPrice</a>	35
<a href="#">Verb</a>	35
<a href="#">Code</a>	36
<a href="#">ConfirmType</a>	36
<a href="#">Country</a>	37
<a href="#">Currency</a>	49
<a href="#">Date</a>	56
<a href="#">DateTime</a>	56
<a href="#">DocumentDateTime</a>	57
<a href="#">Indicator</a>	57
<a href="#">Language</a>	57
<a href="#">ManufacturerPartCode</a>	64

<a href="#">Note</a>	64
<a href="#">PartManufacturerBrand</a>	64
<a href="#">PartMasterCountry</a>	65
<a href="#">PartMasterEffectiveDate</a>	76
<a href="#">PartMasterPriceType</a>	76
<a href="#">PartType</a>	76
<a href="#">PricingCode</a>	77
<a href="#">Reference</a>	77
<a href="#">ReferenceNumber</a>	77
<a href="#">SecondaryPassword</a>	78
<a href="#">ShortMfg</a>	78
<a href="#">SupersedingManufacturerPartCode</a>	78
<a href="#">SystemVersion</a>	78
<a href="#">Text</a>	79
<a href="#">Type</a>	79
<a href="#">UOM</a>	79
<a href="#">URI</a>	80
<a href="#">Fields and Global Attributes</a>	81
<a href="#">ApplicationArea</a>	81
<a href="#">PartMaster</a>	81
<a href="#">PartMasterHeader</a>	82
<a href="#">PartMasterLine</a>	82
<a href="#">Show</a>	83
<a href="#">ShowPartsMaster</a>	84
<a href="#">Verb</a>	84



## Show Parts Master

---

### Show Parts Master Guidelines

## Overview

This document is a guideline on how to use the Show Parts Master Business Object Document (BOD). Show Parts Master has been defined in the context of STAR for the Automotive Retail Industry. The scope of this BOD is to define the Show Parts Master process for individual consumers who service their automobiles through their OEM's authorized Dealers. The focus is on Dealer and OEM interactions, not third party organizations. NOTE: Although this is the traditional use of the Show Parts Master, this BOD could be used to send Show Parts Master information between any two business parties.

Implementation Guidelines provide detailed information regarding the structure and meaning of the Show Parts Master BOD and corresponds directly to the Show Parts Master schema. In addition to structure and meaning, the Implementation Guidelines identify various business rules for specific fields/components that due to their nature, i.e. field interdependence, are not possible to express using schema. Please note that although these business rules are not included in the schema, they **MUST** be followed to be STAR Compliant. Therefore, the Show Parts Master Implementation Guidelines must be used in concert with the Show Parts Master schema during development and should **NOT** be considered a supplement or substitution to the schema. For more information regarding STAR XML Data Compliance, please review the STAR Data Compliance Guidelines document located on the STAR Web site.

For a copy of the corresponding Show Parts Master schema, please download the appropriate STAR schema repository from the XML portion of the STAR website ([www.starstandard.org](http://www.starstandard.org)). Prior to downloading the schema, users are encouraged to download the STAR XML Reference/Implementation document also located on the XML portion of the STAR website. This document provides an overview of the STAR BOD development methodology, how to download and read STAR schema, and various frequently asked questions related to the implementation of STAR BODs.

STAR has followed the Open Application Group's Business Object Document methodology to develop the Show Parts Master BOD. Where possible, STAR has mapped to existing OAGI fields and components. Note however that the STAR Show Parts Master BOD is unique to the Retail Automotive industry and is not an extension of any existing OAGIS BODs.

For more information on the Open Applications Group's BODs and related documentation please refer to the Open Applications Group's Web site at ([www.openapplications.org](http://www.openapplications.org)).

## Schema Field Usage

STAR uses the same Noun in the schema for all the Noun/Verb combinations of the Show Parts Master except the Get verb. Please refer to each Noun/Verb combination within this document to understand the requirements for each specific BOD. Although the Noun will always have every field defined for the Noun in the schema, each Noun/Verb combination may not use all of the fields. If a field is not used by a BOD, it will be noted in the business rules.

## Business Scenario

## Show Parts Master


---

BUSINESS SCENARIO MISSING. Please make sure it is defined in the build script.



### Relationship Diagram

The following is a representation of the Noun for this BOD. It is a high level overview provided to give an idea of the hierarchy of the Noun's components.



### Schema Document Properties

#### Declared Namespaces

A schema can contain more than one namespace. According to Whatis.com, "In general, a namespace uniquely identifies a set of names so that there is no ambiguity when objects having different origins but the same names are mixed together." An example would be two namespaces that both defined an element called ID, without a namespace it would be impossible to determine which definition was being used.

Prefix	Namespace
<b>Default namespace</b>	<a href="http://www.starstandards.org/STAR">http://www.starstandards.org/STAR</a>
<b>xml</b>	<a href="http://www.w3.org/XML/1998/namespace">http://www.w3.org/XML/1998/namespace</a>
<b>xsd</b>	<a href="http://www.w3.org/2001/XMLSchema">http://www.w3.org/2001/XMLSchema</a>

### Components and Data Types

Global definitions include components, code lists, and data types. Components are used to build the data structures that make up a Noun and it's requirements. Data types specify the type of data that a component's fields may contain. Not all definitions are included in this documentation. Please see either the STAR Code List guideline or Data Type Guidelines for further information.

#### Amount

Based on OAGI Amount. Simple content with the currency as an attribute

<b>Name</b>	<b>Amount</b>
<b>Abstract</b>	<b>no</b>

#### Attributes

Field / Component	Description	R/O	Business Rule
currency		R	

#### XML Instance Representation

```
<...  
currency="Currency [1]">  
  xsd:decimal  
</...>
```

#### ApplicationArea

These field(s) use this type: **ApplicationArea**.

<b>Name</b>	<b>ApplicationArea</b>
<b>Abstract</b>	<b>no</b>

#### Data Elements and Components

## Show Parts Master

Field / Component	Description	R/O	Business Rule
Sender	Identifies characteristics and control identifiers that relate to the application that created the Business Object Document. The sender area can indicate the logical location of the application and/or database server, the application, and the task that was processing to create the BOD.	R	
CreationDateTime	is the date time stamp that the given instance of the Business Object Document was created. This date must not be modified during the life of the Business Object Document.	R	
Signature	If the BOD is to be signed the signature element is included, otherwise it is not. Signature supports any digital signature that maybe used by an implementation of OAGIS. The qualifyingAgency identifies the agency that provided the format for the signature. This element supports any digital signature specification that is available today and in the future. This is accomplished by not actually defining the content but by allowing the implementation to specify the digital signature to be used via an external XML Schema namespace declaration. The Signature element is defined to have any content from any other namespace. This allows the user to carry a digital signature in the xml instance of a BOD. The choice of which digital signature to use is left up to the user and their integration needs.	O	
BODId	The BODId provides a place to carry a Globally Unique Identifier (GUID) that will make each Business Object Document instance uniquely identifiable. This is a critical success factor to enable software developers to use the Globally Unique Identifier (GUID) to build the following services or capabilities: 1. Legally binding transactions, 2. Transaction logging, 3. Exception handling, 4. Re-sending, 5. Reporting, 6. Confirmations, 7. Security.	O	
Destination	Information related to the receiver of the BOD	R	

### XML Instance Representation

```
<...>
  <Sender> Sender </Sender> [1]
  <CreationDateTime> DateTime </CreationDateTime> [1]
  <Signature> Signature </Signature> [0..1]
  <BODId> Code </BODId> [0..1]
```

## Show Parts Master

```
<Destination> Destination </Destination> [1]
</...>
```

### BusinessObjectDocument

<b>Name</b>	<b>BusinessObjectDocument</b>
<b>Abstract</b>	<b>no</b>

#### Attributes

Field / Component	Description	R/O	Business Rule
revision	This should contain the STAR repository version in the following recommended format. 4.2.1_M20080416. Where the first part indicates the version of the STAR repository and anything after the _ indicates the Milestone build that is being used. If referring to an official published version then only the STAR Repository version is required.	O	
release	Indicates the OAGIS release that this BOD belongs.	O	
environment	Indicates whether this BOD is being sent in a "Test" or a "Production" mode. If the BOD is being sent in a test mode, it's information should not affect the business operation. However, if the BOD is sent in "Production" mode it is assumed that all test has been complete and the contents of the BOD are to affect the operation of the receiving business application(s).	O	
lang	Indicates the language that the contents of the BOD is in unless otherwise stated.	O	
bodVersion	Deprecated as of STAR 4.2.2. It is recommended to use the revision attribute to identify the repository and the noun. May be removed in a new major version of the STAR repository. Indicates the version number of the BOD.	O	

#### Data Elements and Components

## Show Parts Master

Field / Component	Description	R/O	Business Rule
ApplicationArea	Provides the information that an application may need to know in order to communicate in an integration of two or more business applications. The ApplicationArea is used at the applications layer of communication. While the integration frameworks web services and middleware provide the communication layer that OAGIS operates on top of. Provides the information that an application may need to know in order to communicate in an integration of two or more business applications. The ApplicationArea is used at the applications layer of communication. While the integration frameworks web services and middleware provide the communication layer that OAGIS operates on top of.	R	

### XML Instance Representation

```
<...  
revision="Text [0..1]"  
release="8.1-Lite [0..1]"  
environment="Text [0..1]"  
lang="Language [0..1]"  
bodVersion="Text [0..1]">  
  <ApplicationArea> ... </ApplicationArea> [1]  
</...>
```

### ConfirmableVerb

<b>Name</b>	ConfirmableVerb
<b>Abstract</b>	no

### Attributes

Field / Component	Description	R/O	Business Rule
confirm		R	

### Data Elements and Components

## Show Parts Master

Field / Component	Description	R/O	Business Rule
Verb		R	

### XML Instance Representation

```
<...  
confirm="ConfirmType [0..1]"/>
```

### Description

Description

Name	Description
Abstract	no

### Attributes

Field / Component	Description	R/O	Business Rule
language	The ISO language code that the description is written.	O	

### XML Instance Representation

```
<...  
language="Language [0..1]">  
  xsd:string  
</...>
```

### Destination

These field(s) use this type: **Destination.**

Name	Destination
Abstract	no

### Data Elements and Components

## Show Parts Master

Field / Component	Description	R/O	Business Rule
DestinationNameCode	Code for destination of file (i.e.Short Manufacturer or DSP code)	O	
DestinationURI	Physical address of the destination	O	
DestinationSoftwareCode	Additional information about the destination application	O	
DestinationSoftware	For which software destination file is intended (may not be known).	O	
DealerNumber	Target Dealer Code receiving information	O	
StoreNumber	Dealer code store number (DMS assigned)	O	
AreaNumber	Dealer code area number (DMS vendor assigned)	O	
DealerCountry	Target Dealer country location	O	
PartyId	The Party Id field uniquely identifies the Receiver of the message. This element can be used for parties within the Automotive Community as well as external parties. Party Id is not intended as a replacement for the Dealer Number. Suggested formats for OEMs or other large institutions include: DUNs Number, ShortMfgCode + DUNs, or ShortMfgCode. The suggested format for Dealers is: ShortMfgCode+Dealer Number.	O	
LocationId	The Location Id field uniquely identifies the location of the Receiver of a message. This Id may be aligned with a physical address or data centers. This field provides an additional level of granularity beyond the usage of the Party Id for additional routing and deliver of data.	O	
ServiceId	The Service Id field identifies the particular service to which a message is being sent, e.g., an inventory service.	O	

### XML Instance Representation

```

<...>
  <DestinationNameCode> ShortMfg </DestinationNameCode> [0..1]
  <DestinationURI> URI </DestinationURI> [0..1]
  <DestinationSoftwareCode> Text </DestinationSoftwareCode> [0..1]
  <DestinationSoftware> Text </DestinationSoftware> [0..1]
  <DealerNumber> PartyId </DealerNumber> [0..1]
  <StoreNumber> Text </StoreNumber> [0..1]
  <AreaNumber> Text </AreaNumber> [0..1]

```



## Show Parts Master

```
<DealerCountry> Country </DealerCountry> [0..1]
<PartyId> PartyId </PartyId> [0..1]
<LocationId> LocationId </LocationId> [0..1]
<ServiceId> ServiceId </ServiceId> [0..1]
</...>
```

### DocumentId

These field(s) use this type: **DocumentId**.

Is the identifier for the document.

<b>Name</b>	DocumentId
<b>Abstract</b>	no

### XML Instance Representation

```
<...>
  Id
</...>
```

### HeaderBase

Used on all STAR BODs

<b>Name</b>	HeaderBase
<b>Abstract</b>	no

### Data Elements and Components

Field / Component	Description	R/O	Business Rule
DocumentDateTime	Is the date and time the document was last created. This is not the date and time that the BOD message instance was created.	O	
SecondaryPassword	Secondary password used to validate access to the dealer information	O	
SecondaryDealerNumber	Identifies secondary dealer number if different than primary "Dealer Number"	O	

## Show Parts Master

---

### XML Instance Representation

```
<...>
  <DocumentDateTime> DocumentDateTime </DocumentDateTime> [0..1]
  <SecondaryPassword> SecondaryPassword </SecondaryPassword> [0..1]
  <SecondaryDealerNumber> SecondaryDealerNumber </SecondaryDealerNumber> [0..1]
</...>
```

### Id

These field(s) use this type: **AuthorizationId**.

Party Identification number

Name	Id
Abstract	no

### XML Instance Representation

```
<...>
  xsd:string
</...>
```

### ItemAmount

These field(s) use this type: **ItemAmount**.

Part Core Item Amount

Name	ItemAmount
Abstract	no

### XML Instance Representation

```
<...
currency="Currency [1]">
  Amount
</...>
```

## Show Parts Master

---

### ItemId

These field(s) use this type: ItemId,ItemId.

Item part number

<b>Name</b>	ItemId
<b>Abstract</b>	no

### XML Instance Representation

```
<...>
  Id
</...>
```

### ItemIdDescription

These field(s) use this type: ItemIdDescription.

Item part number detail description

<b>Name</b>	ItemIdDescription
<b>Abstract</b>	no

### XML Instance Representation

```
<...
language="Language [0..1]">
  Description
</...>
```

### ItemQuantity

These field(s) use this type: ItemQuantity.

Quantity of Part number.

<b>Name</b>	ItemQuantity
-------------	--------------

## Show Parts Master

---

<b>Abstract</b>	no
-----------------	----

### XML Instance Representation

```
<...  
  uom="UOM [1]">  
    Quantity  
</...>
```

### LocationId

These field(s) use this type: LocationId,LocationId.

Code identifying a physical location

<b>Name</b>	<b>LocationId</b>
<b>Abstract</b>	no

### XML Instance Representation

```
<...>  
  Id  
</...>
```

### NonTaxableAmount

These field(s) use this type: NonTaxableAmount.

Total non-taxable price.

<b>Name</b>	<b>NonTaxableAmount</b>
<b>Abstract</b>	no

### XML Instance Representation

```
<...  
  currency="Currency [1]">  
    Amount
```

## Show Parts Master

```
</...>
```

### PartCoreDetail

These field(s) use this type: **PartCoreDetail**.

Part Cored Detail

<b>Name</b>	PartCoreDetail
<b>Abstract</b>	no

### Data Elements and Components

Field / Component	Description	R/O	Business Rule
ItemId	Part Item Id	R	
ItemAmount	Part Item Amount	R	

### XML Instance Representation

```
<...>
  <ItemId> ItemId </ItemId> [1]
  <ItemAmount> ItemAmount </ItemAmount> [1]
</...>
```

### PartManufacturer

These field(s) use this type: **PartManufacturer**.

Identifies the part manufacturer.

<b>Name</b>	PartManufacturer
<b>Abstract</b>	no

### XML Instance Representation

```
<...
language="Language [0..1]">
```

## Show Parts Master

Description  
</...>

### PartMaster

These field(s) use this type: **PartMaster**.

<b>Name</b>	PartMaster
<b>Abstract</b>	no

#### Data Elements and Components

Field / Component	Description	R/O	Business Rule
PartMasterHeader	Header Information for the Part Master	R	
PartMasterLine	Line Item Information.	R	

### XML Instance Representation

```
<...>
  <PartMasterHeader> ... </PartMasterHeader> [1]
  <PartMasterLine> ... </PartMasterLine> [1..*]
</...>
```

### PartMasterHeader

These field(s) use this type: **PartMasterHeader**.

<b>Name</b>	PartMasterHeader
<b>Abstract</b>	no

#### Data Elements and Components

Field / Component	Description	R/O	Business Rule
DocumentDateTime	Is the date and time the document was last created. This is not the date and time that the BOD message instance was created.	O	

## Show Parts Master

Field / Component	Description	R/O	Business Rule
SecondaryPassword	Secondary password used to validate access to the dealer information	O	
SecondaryDealerNumber	Identifies secondary dealer number if different than primary "Dealer Number"	O	
DocumentId	Return Number	O	
PartMasterEffectiveDate	Date on which the parts/prices in this document become effective	R	
PartMasterCountry	The ISO Country Codelist that the parts master applies.	R	

### XML Instance Representation

```
<...>
  <DocumentDateTime> DocumentDateTime </DocumentDateTime> [0..1]
  <SecondaryPassword> SecondaryPassword </SecondaryPassword> [0..1]
  <SecondaryDealerNumber> SecondaryDealerNumber </SecondaryDealerNumber> [0..1]
  <DocumentId> DocumentId </DocumentId> [0..1]
  <PartMasterEffectiveDate> PartMasterEffectiveDate </PartMasterEffectiveDate> [1]
  <PartMasterCountry> PartMasterCountry </PartMasterCountry> [1]
</...>
```

### PartMasterLine

These field(s) use this type: **PartMasterLine**.

<b>Name</b>	<b>PartMasterLine</b>
<b>Abstract</b>	<b>no</b>

### Data Elements and Components

Field / Component	Description	R/O	Business Rule
Part	Detail information about the part being returned.	R	
PartManufacturer	Identifes the part manufacturer.	O	
ManufacturerPartCode	Manufacturer's Part Code	O	

## Show Parts Master

Field / Component	Description	R/O	Business Rule
PartManufacturerBrand	Manufacturer Brand Name for the Part	O	
ItemQuantity	Quantity of part.	O	
PartMasterPricing	Pricing for the Part Master	O	
PartCoreDetail	Part Core Detail information	O	
SupersedingPartGroup	Part Core Detail information	O	
TopSellerGroup	Top Selling Brands for this Part.	O	

### XML Instance Representation

```
<...>
  <Part> PartsBase </Part> [1]
  <PartManufacturer> PartManufacturer </PartManufacturer> [0..1]
  <ManufacturerPartCode> ManufacturerPartCode </ManufacturerPartCode> [0..1]
  <PartManufacturerBrand> PartManufacturerBrand </PartManufacturerBrand> [0..1]
  <ItemQuantity> ItemQuantity </ItemQuantity> [0..1]
  <PartMasterPricing> PartMasterPricing </PartMasterPricing> [0..*]
  <PartCoreDetail> PartCoreDetail </PartCoreDetail> [0..*]
  <SupersedingPartGroup> SupersedingPartGroup </SupersedingPartGroup> [0..*]
  <TopSellerGroup> TopSeller </TopSellerGroup> [0..1]
</...>
```

### PartMasterPricing

These field(s) use this type: **PartMasterPricing**.

Pricing for the Item in the Parts Master.

<b>Name</b>	<b>PartMasterPricing</b>
<b>Abstract</b>	<b>no</b>

### Data Elements and Components



## Show Parts Master

Field / Component	Description	R/O	Business Rule
PartMasterPriceType	Type of Pricing.	R	
QuantityDiscounts	Lists the Quantity Discounts available for this part.	O	
TaxableAmount	Taxable Amount	O	
NonTaxableAmount	Nontaxable Amount	O	
TotalAmount	Total Amount	O	
UnitPrice	Unit Price	O	

### XML Instance Representation

```
<...>
  <PartMasterPriceType> PartMasterPriceType </PartMasterPriceType> [1]
  <QuantityDiscounts> QuantityDiscounts </QuantityDiscounts> [0..*]
  <TaxableAmount> TaxableAmount </TaxableAmount> [0..1]
  <NonTaxableAmount> NonTaxableAmount </NonTaxableAmount> [0..1]
  <TotalAmount> TotalAmount </TotalAmount> [0..1]
  <UnitPrice> UnitPrice </UnitPrice> [0..1]
</...>
```

## PartsBase

These field(s) use this type: **Part**.

<b>Name</b>	PartsBase
<b>Abstract</b>	no

### Data Elements and Components

Field / Component	Description	R/O	Business Rule
ItemId	Item part number identifier	O	
ItemIdDescription	Item part number detail description	O	

## Show Parts Master

Field / Component	Description	R/O	Business Rule
PartType	Specifies whether the parts are indicated by manufacturer part code or Part Number	O	
SupplierItemId	Supplier identification of part on order.	O	

### XML Instance Representation

```
<...>
  <ItemId> ItemId </ItemId> [0..1]
  <ItemIdDescription> ItemIdDescription </ItemIdDescription> [0..1]
  <PartType> PartType </PartType> [0..1]
  <SupplierItemId> SupplierItemId </SupplierItemId> [0..1]
</...>
```

## PartSupersedingGroup

These field(s) use this type: **PartSupersedingGroup**.

A group of superseding parts for a superseded part.

<b>Name</b>	PartSupersedingGroup
<b>Abstract</b>	no

### Data Elements and Components

Field / Component	Description	R/O	Business Rule
SupersedingPartNumberUID	The superseding part number used for lookup.	R	

### XML Instance Representation

```
<...>
  <SupersedingPartNumberUID> SupersedingPartNumberUID </SupersedingPartNumberUID> [1..*]
</...>
```

## PartyId

## Show Parts Master

---

These field(s) use this type: DealerNumber,PartyId,DealerNumber,PartyId.

Party Identification Number

<b>Name</b>	PartyId
<b>Abstract</b>	no

### XML Instance Representation

```
<...>  
  Id  
</...>
```

## Quantity

A decimal value with uom

<b>Name</b>	Quantity
<b>Abstract</b>	no

### Attributes

Field / Component	Description	R/O	Business Rule
uom		R	

### XML Instance Representation

```
<...  
uom="UOM [1]">  
  xsd:decimal  
</...>
```

## QuantityDiscounts

These field(s) use this type: QuantityDiscounts.

Pricing discounts for a core part.

## Show Parts Master

<b>Name</b>	QuantityDiscounts
<b>Abstract</b>	no

### Data Elements and Components

Field / Component	Description	R/O	Business Rule
PricingCode	The core part code.	R	

### XML Instance Representation

```
<...>  
  <PricingCode> PricingCode </PricingCode> [1]  
</...>
```

## ResponseVerb

<b>Name</b>	ResponseVerb
<b>Abstract</b>	no

### Data Elements and Components

Field / Component	Description	R/O	Business Rule
Verb		R	
OriginalBODId		O	

### XML Instance Representation

```
<...  
confirm="ConfirmType [0..1]">  
  <OriginalBODId> xsd:NMTOKEN </OriginalBODId> [0..1]  
</...>
```

## SecondaryDealerNumber

## Show Parts Master

These field(s) use this type: **SecondaryDealerNumber**.

Identifies secondary dealer number if different than primary "Dealer Number"

<b>Name</b>	<b>SecondaryDealerNumber</b>
<b>Abstract</b>	<b>no</b>

### XML Instance Representation

```
<...>  
  Id  
</...>
```

## Sender

These field(s) use this type: **Sender**.

<b>Name</b>	<b>Sender</b>
<b>Abstract</b>	<b>no</b>

## Data Elements and Components

Field / Component	Description	R/O	Business Rule
LogicalId	Provides the logical location of the server and applications from which the Business Object Document originated. It can be used to establish a logical to physical mapping, however its use is optional. Each system or combination of systems should maintain an external central reference table containing the logical names or logical addresses of the application systems in the integration configuration. This enables the logical names to be mapped to the physical network addresses of the resources needed on the network. Note: The technical implementation of this Domain Naming Service is not dictated by this specification. This logical to physical mapping may be done at execution time by the application itself or by a middleware transport mechanism, depending on the integration architecture used. This provides for a simple but effective directory access capability while maintaining application independence from the physical location of those resources on the network	O	

## Show Parts Master

Field / Component	Description	R/O	Business Rule
Component	Provides a finer level of control than Logical Identifier and represents the business application that issued the Business Object Document. Its use is optional. For STAR's use this is the DCS Software code name		
Task	Describes the business event that initiated the need for the Business Object Document to be created. For STAR, the task is defined in the Implementation Guidelines for each BOD. It is usually a short description of the BOD. Ex: SalesLead, CreditDecision, etc.	R	
ReferenceId	Enables the sending application to indicate the instance identifier of the event or task that caused the BOD to be created. This is used to correlate a response BOD to an originating BOD	O	
AuthorizationId	Identifies the authorization level of the user or application that is sending the Business Object Document Message. This authorization level being recognized by the receiving system indicates what can be done on the receiving system. For STAR, this is the User ID.	O	
CreatorNameCode	DCS Software Creator Code	R	
SenderNameCode	Additional information about the sending platform (i.e., Short MFG or DSP code).	R	
SenderURI	Physical address of the sender	O	
DealerNumber	Dealer Code of source of information	O	
StoreNumber	Dealer code store number (DMS assigned)	O	
AreaNumber	Dealer code area number (DMS vendor assigned)	O	
DealerCountry	Source Dealer country location	O	
Language	This code is used to define the language of the data used in this transaction	O	
DeliverPendingMailInd	Indicates if the user requests to receive pending mail that has been stored and has yet not been delivered yet. By selecting 0, the user will only receive the response for the current transaction the user is performing.	O	
Password	Token for application specific authentication. Used to authenticate dealership/users through application specific security	O	

## Show Parts Master

Field / Component	Description	R/O	Business Rule
SystemVersion	The sender's software version number.	O	
PartyId	The Party Id field uniquely identifies the Sender of the message. This element can be used for parties within the Automotive Community as well as external parties. Party Id is not intended as a replacement for the Dealer Number. Suggested formats for OEMs or other large institutions include: DUNs Number, ShortMfgCode + DUNs, or ShortMfgCode. The suggested format for Dealers is: ShortMfgCode+Dealer Number.	O	
LocationId	The Location Id field uniquely identifies the location of the Sender of a message. This Id may be aligned with a physical address or data centers. This field provides an additional level of granularity beyond the usage of the Party Id for additional routing and deliver of data.	O	
ServiceId	The Service Id field identifies the particular service from which a message is being sent, e.g., an inventory service.	O	

### XML Instance Representation

```

<...>
  <LogicalId> Text </LogicalId> [0..1]
  <Component> Text </Component> [1]
  <Task> Text </Task> [1]
  <ReferenceId> Reference </ReferenceId> [0..1]
  <AuthorizationId> Id </AuthorizationId> [0..1]
  <CreatorNameCode> Text </CreatorNameCode> [1]
  <SenderNameCode> ShortMfg </SenderNameCode> [1]
  <SenderURI> URI </SenderURI> [0..1]
  <DealerNumber> PartyId </DealerNumber> [0..1]
  <StoreNumber> Text </StoreNumber> [0..1]
  <AreaNumber> Text </AreaNumber> [0..1]
  <DealerCountry> Country </DealerCountry> [0..1]
  <Language> Language </Language> [0..1]
  <DeliverPendingMailInd> Indicator </DeliverPendingMailInd> [0..1]
  <Password> Text </Password> [0..1]
  <SystemVersion> SystemVersion </SystemVersion> [0..1]
  <PartyId> PartyId </PartyId> [0..1]
  <LocationId> LocationId </LocationId> [0..1]

```

## Show Parts Master

```
<ServiceId> ServiceId </ServiceId> [0..1]
</...>
```

### SenderBase

<b>Name</b>	SenderBase
<b>Abstract</b>	no

### Data Elements and Components

Field / Component	Description	R/O	Business Rule
LogicalId	Provides the logical location of the server and applications from which the Business Object Document originated. It can be used to establish a logical to physical mapping, however its use is optional. Each system or combination of systems should maintain an external central reference table containing the logical names or logical addresses of the application systems in the integration configuration. This enables the logical names to be mapped to the physical network addresses of the resources needed on the network. Note: The technical implementation of this Domain Naming Service is not dictated by this specification. This logical to physical mapping may be done at execution time by the application itself or by a middleware transport mechanism, depending on the integration architecture used. This provides for a simple but effective directory access capability while maintaining application independence from the physical location of those resources on the network	O	
Component	Provides a finer level of control than Logical Identifier and represents the business application that issued the Business Object Document. Its use is optional. For STAR's use this is the DCS Software code name		
Task	Describes the business event that initiated the need for the Business Object Document to be created. For STAR, the task is defined in the Implementation Guidelines for each BOD. It is usually a short description of the BOD. Ex: SalesLead, CreditDecision, etc.	R	
ReferenceId	Enables the sending application to indicate the instance identifier of the event or task that caused the BOD to be created. This is used to correlate a response BOD to an originating BOD	O	



## Show Parts Master

Field / Component	Description	R/O	Business Rule
AuthorizationId	Identifies the authorization level of the user or application that is sending the Business Object Document Message. This authorization level being recognized by the receiving system indicates what can be done on the receiving system. For STAR, this is the User ID.	O	

### XML Instance Representation

```
<...>
  <LogicalId> Text </LogicalId> [0..1]
  <Component> Text </Component> [1]
  <Task> Text </Task> [1]
  <ReferenceId> Reference </ReferenceId> [0..1]
  <AuthorizationId> Id </AuthorizationId> [0..1]
</...>
```

## ServiceId

These field(s) use this type: **ServiceId,ServiceId**.

The Service Id field identifies the particular service to or from which a message is being sent, e.g., an inventory service.

<b>Name</b>	<b>ServiceId</b>
<b>Abstract</b>	no

### XML Instance Representation

```
<...>
  Id
</...>
```

## Show

These field(s) use this type: **Show**.

<b>Name</b>	<b>Show</b>
-------------	-------------

## Show Parts Master

**Abstract** no

### Data Elements and Components

Field / Component	Description	R/O	Business Rule
Verb		R	
OriginalBODId		O	

### XML Instance Representation

```
<...  
confirm="ConfirmType [0..1]">  
  <OriginalBODId> xsd:NMTOKEN </OriginalBODId> [0..1]  
</...>
```

## ShowPartsMaster

These field(s) use this type: ShowPartsMaster.

**Name** ShowPartsMaster

**Abstract** no

### Data Elements and Components

Field / Component	Description	R/O	Business Rule
ApplicationArea	Provides the information that an application may need to know in order to communicate in an integration of two or more business applications. The ApplicationArea is used at the applications layer of communication. While the integration frameworks web services and middleware provide the communication layer that OAGIS operates on top of. Provides the information that an application may need to know in order to communicate in an integration of two or more business applications. The ApplicationArea is used at the applications layer of communication. While the integration frameworks web services and middleware provide the communication layer that OAGIS operates on top of.	R	

## Show Parts Master

Field / Component	Description	R/O	Business Rule
DataArea		R	

### XML Instance Representation

```
<...
revision="Text [0..1]"
release="8.1-Lite [0..1]"
environment="Text [0..1]"
lang="Language [0..1]"
bodVersion="Text [0..1]">
  <ApplicationArea> ... </ApplicationArea> [1]
  <DataArea> ShowPartsMasterDataArea </DataArea> [1]
</...>
```

### ShowPartsMasterDataArea

These field(s) use this type: DataArea.

Name	ShowPartsMasterDataArea
Abstract	no

### Data Elements and Components

## Show Parts Master

Field / Component	Description	R/O	Business Rule
Show	The Show verb is used when sending the information about a specific instance of a business document or entity. The Show verb may be used to respond to a Get request or it can be used in a publish scenario, where it pushes information to other applications based on a business event. Although BODs based on this verb do not commonly cause updates to occur, there may be times when the component receiving the Show decides to use the information it receives to update. This is entirely the decision of the receiving software component and is not forbidden. The behavior of the Show verb is quite straight forward with one exception. The Show response to any Get request needs to read the request carefully to ensure the response is returning the requested Data Types.	R	
PartMaster		R	

### XML Instance Representation

```
<...>
  <Show> ... </Show> [1]
  <PartMaster> ... </PartMaster> [1..*]
</...>
```

### Signature

These field(s) use this type: **Signature**.

Name	Signature
Abstract	no

### Attributes

Field / Component	Description	R/O	Business Rule
qualifyingAgency		O	

### Data Elements and Components

## Show Parts Master

Field / Component	Description	R/O	Business Rule
-------------------	-------------	-----	---------------

### XML Instance Representation

```
<...  
qualifyingAgency="Text [0..1]">  
Allow any elements from any namespace (strict validation). [0..1]  
</...>
```

### SupersedingItemDescription

These field(s) use this type: **SupersedingItemDescription**.

Description of superseding item.

<b>Name</b>	SupersedingItemDescription
<b>Abstract</b>	no

### XML Instance Representation

```
<...  
language="Language [0..1]">  
  Description  
</...>
```

### SupersedingPartDetail

These field(s) use this type: **SupersedingPartDetail**.

Top Sellers

<b>Name</b>	SupersedingPartDetail
<b>Abstract</b>	no

## Data Elements and Components

## Show Parts Master

Field / Component	Description	R/O	Business Rule
SupersedingPartNumber	Superseding Item Number	R	
SupersedingManufacturerPartCode	Manufacturer assigned part code for superseding part.	O	
SupersedingItemDescription	Description of superseding item.	O	
PartSupersedingGroup	Contains a grouping of part numbers that superseded this superseded part.	O	

### XML Instance Representation

```
<...>  
  <SupersedingPartNumber> SupersedingPartNumber </SupersedingPartNumber> [1]  
  <SupersedingManufacturerPartCode> SupersedingManufacturerPartCode </SupersedingManufacturerPartCode> [0..1]  
  <SupersedingItemDescription> SupersedingItemDescription </SupersedingItemDescription> [0..1]  
  <PartSupersedingGroup> PartSupersedingGroup </PartSupersedingGroup> [0..1]  
</...>
```

## SupersedingPartGroup

These field(s) use this type: **SupersedingPartGroup**.

A group of superseding parts for a particular item number.

<b>Name</b>	<b>SupersedingPartGroup</b>
<b>Abstract</b>	<b>no</b>

### Data Elements and Components

Field / Component	Description	R/O	Business Rule
SupersedingPartDetail	Detail information for superseding items.	R	

### XML Instance Representation

```
<...>  
  <SupersedingPartDetail> SupersedingPartDetail </SupersedingPartDetail> [1..*]  
</...>
```

## Show Parts Master

---

### SupersedingPartNumber

These field(s) use this type: SupersedingPartNumber.

Part number superseding this one.

<b>Name</b>	SupersedingPartNumber
<b>Abstract</b>	no

#### XML Instance Representation

```
<...>
  ItemId
</...>
```

### SupersedingPartNumberUID

These field(s) use this type: SupersedingPartNumberUID.

Part Number key used for look up of superseded parts.

<b>Name</b>	SupersedingPartNumberUID
<b>Abstract</b>	no

#### XML Instance Representation

```
<...>
  ItemId
</...>
```

### SupplierItemId

These field(s) use this type: SupplierItemId.

Supplier identification of part on order.

<b>Name</b>	SupplierItemId
<b>Abstract</b>	no

## Show Parts Master

---

### XML Instance Representation

```
<...>
  ItemId
</...>
```

### TaxableAmount

These field(s) use this type: **TaxableAmount**.

Total Taxable Price

Name	TaxableAmount
Abstract	no

### XML Instance Representation

```
<...
currency="Currency [1]">
  Amount
</...>
```

### TopSeller

These field(s) use this type: **TopSellerGroup**.

Top Sellers

Name	TopSeller
Abstract	no

### Data Elements and Components

Field / Component	Description	R/O	Business Rule
PartManufacturerBrand	Top Selling Brands for this Part.	R	

### XML Instance Representation



## Show Parts Master

---

```
<...>
  <PartManufacturerBrand> PartManufacturerBrand </PartManufacturerBrand> [1..*]
</...>
```

### TotalAmount

These field(s) use this type: **TotalAmount**.

Total price (cost + markup)

<b>Name</b>	<b>TotalAmount</b>
<b>Abstract</b>	<b>no</b>

### XML Instance Representation

```
<...
currency="Currency [1]">
  Amount
</...>
```

### UnitPrice

These field(s) use this type: **UnitPrice**.

UnitPrice

<b>Name</b>	<b>UnitPrice</b>
<b>Abstract</b>	<b>no</b>

### XML Instance Representation

```
<...
currency="Currency [1]">
  Amount
</...>
```

### Verb

## Show Parts Master

These field(s) use this type: Verb.

<b>Name</b>	Verb
<b>Abstract</b>	no

### Data Elements and Components

Field / Component	Description	R/O	Business Rule
-------------------	-------------	-----	---------------

#### XML Instance Representation

```
<.../>
```

## Code

These field(s) use this type: BODId.

Unique code name

<b>Name</b>	<b>Code</b>
-------------	-------------

\*Base XSD Type: string

## ConfirmType

<b>Name</b>	<b>ConfirmType</b>
-------------	--------------------

\*Base XSD Type: NMTOKEN

Code Value	Description
Always	
OnChange	
Never	

### Country

These field(s) use this type: **DealerCountry,DealerCountry.**

Country in which the Address is in. Conforms to ISO 3166-2. AF -AFGHANISTAN AL -ALBANIA DZ -ALGERIA AS -AMERICAN SAMOA AD -ANDORRA AO -ANGOLA AI -ANGUILLA AQ -ANTARCTICA AG -ANTIGUA AND BARBUDA AR -ARGENTINA AM -ARMENIA AW -ARUBA AU -AUSTRALIA AT -AUSTRIA AZ -AZERBAIJAN BS -BAHAMAS BH -BAHRAIN BD -BANGLADESH BB -BARBADOS BY -BELARUS BE -BELGIUM BZ -BELIZE BJ -BENIN BM -BERMUDA BT -BHUTAN BO -BOLIVIA BA -BOSNIA AND HERZEGOVINA BW -BOTSWANA BV -BOUVET ISLAND BR -BRAZIL IO -BRITISH INDIAN OCEAN TERRITORY BN -BRUNEI DARUSSALAM BG -BULGARIA BF -BURKINA FASO BI -BURUNDI KH -CAMBODIA CM -CAMEROON CA -CANADA CV -CAPE VERDE KY -CAYMAN ISLANDS CF -CENTRAL AFRICAN REPUBLIC TD -CHAD CL -CHILE CN -CHINA CX -CHRISTMAS ISLAND CC -COCOS (KEELING) ISLANDS CO -COLOMBIA KM -COMOROS CG -CONGO CD -CONGO, THE DEMOCRATIC REPUBLIC OF THE CK -COOK ISLANDS CR -COSTA RICA CI -CÔTE D'IVOIRE HR -CROATIA CU -CUBA CY -CYPRUS CZ -CZECH REPUBLIC DK -DENMARK DJ -DJIBOUTI DM -DOMINICA DO -DOMINICAN REPUBLIC EC -ECUADOR EG -EGYPT SV -EL SALVADOR GQ -EQUATORIAL GUINEA ER -ERITREA EE -ESTONIA ET -ETHIOPIA FK -FALKLAND ISLANDS (MALVINAS) FO -FAROE ISLANDS FJ -FIJI FI -FINLAND FR -FRANCE GF -FRENCH GUIANA PF -FRENCH POLYNESIA TF -FRENCH SOUTHERN TERRITORIES GA -GABON GM -GAMBIA GE -GEORGIA DE -GERMANY GH -GHANA GI -GIBRALTAR GR -GREECE GL -GREENLAND GD -GRENADA GP -GUADELOUPE GU -GUAM GT -GUATEMALA GN -GUINEA GW -GUINEA-BISSAU GY -GUYANA HT -HAITI HM -HEARD ISLAND AND MCDONALD ISLANDS VA -HOLY SEE (VATICAN CITY STATE) HN -HONDURAS HK -HONG KONG HU -HUNGARY IS -ICELAND IN -INDIA ID -INDONESIA IR -IRAN, ISLAMIC REPUBLIC OF IQ -IRAQ IE -IRELAND IL -ISRAEL IT -ITALY JM -JAMAICA JP -JAPAN JO -JORDAN KZ -KAZAKHSTAN KE -KENYA KI -KIRIBATI KP -KOREA, DEMOCRATIC PEOPLE'S REPUBLIC OF KR -KOREA, REPUBLIC OF KW -KUWAIT KG -KYRGYZSTAN LA -LAO PEOPLE'S DEMOCRATIC REPUBLIC LV -LATVIA LB -LEBANON LS -LESOTHO LR -LIBERIA LY -LIBYAN ARAB JAMAHIRIYA LI -LIECHTENSTEIN LT -LITHUANIA LU -LUXEMBOURG MO -MACAO MK -MACEDONIA, THE FORMER YUGOSLAV REPUBLIC OF MG -MADAGASCAR MW -MALAWI MY -MALAYSIA MV -MALDIVES ML -MALI MT -MALTA MH -MARSHALL ISLANDS MQ -MARTINIQUE MR -MAURITANIA MU -MAURITIUS YT -MAYOTTE MX -MEXICO FM -MICRONESIA, FEDERATED STATES OF MD -MOLDOVA, REPUBLIC OF MC -MONACO MN -MONGOLIA MS -MONTSERRAT MA -MOROCCO MZ -MOZAMBIQUE MM -MYANMAR NA -NAMIBIA NR -NAURU NP -NEPAL NL -NETHERLANDS AN -NETHERLANDS ANTILLES NC -NEW CALEDONIA NZ -NEW ZEALAND NI -NICARAGUA NE -NIGER NG -NIGERIA NU -NIUE NF -NORFOLK ISLAND MP -NORTHERN MARIANA ISLANDS NO -NORWAY OM -OMAN PK -PAKISTAN PW -PALAU PS -PALESTINIAN TERRITORY, OCCUPIED PA -PANAMA PG -PAPUA NEW GUINEA PY -PARAGUAY PE -PERU PH -PHILIPPINES PN -PITCAIRN PL -POLAND PT -PORTUGAL PR -PUERTO RICO QA -QATAR RE -RÅÅ#UNION RO -ROMANIA RU -RUSSIAN FEDERATION RW -RWANDA SH -SAINT HELENA KN -SAINT KITTS AND NEVIS LC -SAINT LUCIA PM -SAINT PIERRE AND MIQUELON VC -SAINT VINCENT AND THE GRENADINES WS -SAMOA SM -SAN MARINO ST -SAO TOME AND PRINCIPE SA -SAUDI ARABIA SN -SENEGAL CS -SERBIA AND MONTENEGRO SC -SEYCHELLES SL -SIERRA LEONE SG -SINGAPORE SK -SLOVAKIA SI -SLOVENIA SB -SOLOMON ISLANDS SO -SOMALIA ZA -SOUTH AFRICA GS -SOUTH GEORGIA AND THE SOUTH SANDWICH ISLANDS ES -SPAIN LK -SRI LANKA SD -SUDAN SR -SURINAME SJ -SVALBARD AND JAN MAYEN SZ -SWAZILAND SE -SWEDEN CH -SWITZERLAND SY -SYRIAN ARAB REPUBLIC TW -TAIWAN, PROVINCE OF CHINA TJ -TAJIKISTAN TZ -TANZANIA, UNITED REPUBLIC OF TH -THAILAND TL -TIMOR-LESTE TG - TOGO TK -TOKELAU TO -TONGA TT -TRINIDAD AND TOBAGO TN -TUNISIA TR -TURKEY TM

## Show Parts Master

-TURKMENISTAN TC -TURKS AND CAICOS ISLANDS TV -TUVALU UG -UGANDA UA -UKRAINE AE -UNITED ARAB EMIRATES GB  
-UNITED KINGDOM US -UNITED STATES UM -UNITED STATES MINOR OUTLYING ISLANDS UY -URUGUAY UZ -UZBEKISTAN VU  
-VANUATU VE -VENEZUELA VN -VIET NAM VG -VIRGIN ISLANDS, BRITISH VI -VIRGIN ISLANDS, U.S. WF -WALLIS AND FUTUNA EH  
-WESTERN SAHARA YE -YEMEN ZM -ZAMBIA ZW -ZIMBABWE

Name	Country
------	---------

\*Base XSD Type: string

Code Value	Description
US	
AF	
AL	
DZ	
AS	
AD	
AO	
AI	
AQ	
AG	
AR	
AM	
AW	
AU	
AT	
AZ	
BS	

## Show Parts Master

Code Value	Description
BH	
BD	
BB	
BY	
BE	
BZ	
BJ	
BM	
BT	
BO	
BA	
BW	
BV	
BR	
IO	
BN	
BG	
BF	
BI	
KH	
CM	
CA	

## Show Parts Master

Code Value	Description
CV	
KY	
CF	
TD	
CL	
CN	
CX	
CC	
CO	
KM	
CG	
CD	
CK	
CR	
CI	
HR	
CU	
CY	
CZ	
DK	
DJ	
DM	

## Show Parts Master

Code Value	Description
DO	
EC	
EG	
SV	
GQ	
ER	
EE	
ET	
FK	
FO	
FJ	
FI	
FR	
GF	
PF	
TF	
GA	
GM	
GE	
DE	
GH	
GI	

## Show Parts Master

Code Value	Description
GR	
GL	
GD	
GP	
GU	
GT	
GN	
GW	
GY	
HT	
HM	
VA	
HN	
HK	
HU	
IS	
IN	
ID	
IR	
IQ	
IE	
IL	



## Show Parts Master

Code Value	Description
IT	
JM	
JP	
JO	
KZ	
KE	
KI	
KP	
KR	
KW	
KG	
LA	
LV	
LB	
LS	
LR	
LY	
LI	
LT	
LU	
MO	
MK	

## Show Parts Master

---

Code Value	Description
MG	
MW	
MY	
MV	
ML	
MT	
MH	
MQ	
MR	
MU	
YT	
MX	
FM	
MD	
MC	
MN	
MS	
MA	
MZ	
MM	
NA	
NR	

## Show Parts Master

---

Code Value	Description
NP	
NL	
AN	
NC	
NZ	
NI	
NE	
NG	
NU	
NF	
MP	
NO	
OM	
PK	
PW	
PS	
PA	
PG	
PY	
PE	
PH	
PN	

## Show Parts Master

Code Value	Description
PL	
PT	
PR	
QA	
RE	
RO	
RU	
RW	
SH	
KN	
LC	
PM	
VC	
WS	
SM	
ST	
SA	
SN	
CS	
SC	
SL	
SG	

## Show Parts Master

Code Value	Description
SK	
SI	
SB	
SO	
ZA	
GS	
ES	
LK	
SD	
SR	
SJ	
SZ	
SE	
CH	
SY	
TW	
TJ	
TZ	
TH	
TL	
TG	
TK	

## Show Parts Master

---

Code Value	Description
TO	
TT	
TN	
TR	
TM	
TC	
TV	
UG	
UA	
AE	
GB	
UM	
UY	
UZ	
VU	
VE	
VN	
VG	
VI	
WF	
EH	
YE	

## Show Parts Master

Code Value	Description
ZM	
ZW	

## Currency

The ISO code identifying the type of currency in use.

Name	Currency
Base XSD Type: string	
Code Value	Description
USD	
ADP	
AED	
AFA	
ALL	
ANG	
AOK	
ARA	
ATS	
AUD	
AWG	
BBD	
BDT	
BEF	

## Show Parts Master

Code Value	Description
BGL	
BHD	
BIF	
BMD	
BND	
BOB	
BRC	
BSD	
BTN	
BUK	
BWP	
BZD	
CAD	
CHF	
CLF	
CLP	
CNY	
COP	
CRC	
CSK	
CUP	
CVE	



## Show Parts Master

Code Value	Description
CYP	
DDM	
DEM	
DJF	
DKK	
DOP	
DZD	
ECS	
EGP	
ESP	
ETB	
EUR	
FIM	
FKP	
FRF	
GBP	
GHC	
GIP	
GMD	
GNF	
GRD	
GTQ	

## Show Parts Master

Code Value	Description
GWP	
GYD	
HKD	
HNL	
HTG	
HUF	
IDR	
IEP	
ILS	
INR	
IQD	
IRR	
ISK	
ITL	
JMD	
JOD	
JPY	
KES	
KHR	
KMF	
KPW	
KRW	

## Show Parts Master

Code Value	Description
KWD	
KYD	
LAK	
LBP	
LKR	
LRD	
LSL	
LUF	
LYD	
MAD	
MGF	
MNT	
MOP	
MRO	
MTL	
MUR	
MVR	
MWK	
MXN	
MYR	
MZM	
NGN	

## Show Parts Master

---

Code Value	Description
NIC	
NLG	
NOK	
NPR	
NZD	
OMR	
PAB	
PEI	
PGK	
PHP	
PKR	
PLZ	
PTE	
PYG	
QAR	
ROL	
RWF	
SAR	
SBD	
SCR	
SDP	
SEK	

## Show Parts Master

---

Code Value	Description
SGD	
SHP	
SLL	
SKK	
SOS	
SRG	
STD	
SUR	
SVC	
SYP	
SZL	
THB	
TND	
TOP	
TPE	
TRL	
TTD	
TWD	
TZS	
UGS	
UYP	
VEB	

## Show Parts Master

Code Value	Description
VND	
VUV	
WST	
YDD	
YER	
YUD	
ZAR	
ZRZ	
ZWD	
Other	

### Date

Date conforms to ISO 8601 format rules EX: \d\d\d\d-\d\d-\d\d

Name	Date
------	------

\*Base XSD Type: date

### DateTime

These field(s) use this type: CreationDateTime.

Date and time conforms to ISO 8601format rules without offset EX:2003-11-05T13:15:30Z

Name	DateTime
------	----------

\*Base XSD Type: dateTime

## Show Parts Master

### DocumentDateTime

These field(s) use this type: **DocumentDateTime**.

Is the date and time the document was last created. This is not the date and time that the BOD message instance was created.

Name	DocumentDateTime
*Base XSD Type: dateTime	

### Indicator

These field(s) use this type: **DeliverPendingMailInd.**

0 = No, 1 = Yes

Name	Indicator
*Base XSD Type: string	
Code Value	Description
0	
1	

### Language

These field(s) use this type: **Language**.

Language conforms to ISO 639-2 rules. Note the format for this field is language-Country (see Country data type for the list of countries with definitions). AA "Afar", AB "Abkhazian", AF "Afrikaans", AM "Amharic", AR "Arabic", AS "Assamese", AY "Aymara", AZ "Azerbaijani", BA "Bashkir", BE "Byelorussian", BG "Bulgarian", BH "Bihari", BI "Bislama", BN "Bengali" "Bangla", BO "Tibetan", BR "Breton", CA "Catalan", CO "Corsican", CS "Czech", CY "Welsh", DA "Danish", DE "German", DZ "Bhutani", EL "Greek", EN "English" "American", ES "Spanish", ET "Estonian", EU "Basque", FA "Persian", FI "Finnish", FJ "Fiji", FO "Faeroese", FR "French", FY "Frisian", GA "Irish", GD "Gaelic" "Scots Gaelic", GL "Galician", GN "Guarani", GU "Gujarati", HA "Hausa", HI "Hindi", HR "Croatian", HU "Hungarian", HY "Armenian", IK "Inupiak", IN "Indonesian", IS "Icelandic", IT "Italian", IW "Hebrew", JA "Japanese", JI "Yiddish", JW "Javanese", KA "Georgian", KK "Kazakh", KL "Greenlandic", KM "Cambodian", KN "Kannada", KO "Korean", KS "Kashmiri", KU "Kurdish", KY "Kirghiz", LA "Latin", LN "Lingala", LO "Laothian", LT "Lithuanian", LV "Latvian" "Lettish", MG "Malagasy", MI "Maori", MK "Macedonian", ML "Malayalam", MN "Mongolian", MO "Moldavian", MR "Marathi", MS "Malay", MT "Maltese", MY

## Show Parts Master

"Burmese", NA "Nauru", NE "Nepali", NL "Dutch", NO "Norwegian", OC "Occitan", OM "Oromo" "Afan", OR "Oriya", PA "Punjabi", PL "Polish", PS "Pashto" "Pushto", PT "Portuguese", QU "Quechua", RM "Rhaeto-Romance", RN "Kirundi", RO "Romanian", RU "Russian", RW "Kinyarwanda", SA "Sanskrit", SD "Sindhi", SG "Sangro", SH "Serbo-Croatian", SI "Singhalese", SK "Slovak", SL "Slovenian", SM "Samoan", SN "Shona", SO "Somali", SQ "Albanian", SR "Serbian", SS "Siswati", ST "Sesotho", SU "Sudanese", SV "Swedish", SW "Swahili", TA "Tamil", TE "Tegulu", TG "Tajik", TH "Thai", TI "Tigrinya", TK "Turkmen", TL "Tagalog", TN "Setswana", TO "Tonga", TR "Turkish", TS "Tsonga", TT "Tatar", TW "Twi", UK "Ukrainian", UR "Urdu", UZ "Uzbek", VI "Vietnamese", WO "Wolof", XH "Xhosa", YO "Yoruba", ZH "Chinese", ZU "Zulu"

Name	Language
------	----------

Base XSD Type: string

Code Value	Description
en-US	
en-CA	
aa-ET	
ab-GE	
af-ZA	
am-ET	
ar-SA	
as-IN	
ay-BO	
az-AZ	
ba-RU	
be-BY	
bg-BG	
bh-IN	
bi-VU	
bn-BD	



## Show Parts Master

---

Code Value	Description
bo-BT	
br-FR	
ca-ES	
co-FR	
cs-CZ	
cy-GB	
da-DE	
de-DE	
dz-BT	
el-GR	
es-ES	
et-EE	
eu-ES	
fa-AF	
fi-FI	
fj-FJ	
fo-FO	
fr-CA	
fr-FR	
fy-NL	
ga-IE	
gd-GB	

## Show Parts Master

Code Value	Description
gl-ES	
gn-PY	
gu-IN	
ha-NG	
hi-IN	
hr-HR	
hu-HU	
hy-AM	
ik-GL	
in-ID	
is-IS	
it-IT	
iw-IL	
ja-JP	
ji-IL	
jw-ID	
ka-GE	
kk-KZ	
kl-GL	
km-KH	
kn-IN	
ko-KP	

## Show Parts Master

Code Value	Description
ko-KR	
ks-IN	
ku-IQ	
ky-CN	
la-VA	
ln-CD	
lo-LA	
lt-LT	
lv-LV	
mg-MG	
mi-NZ	
mk-MK	
ml-IN	
mn-MN	
mo-MO	
mr-IN	
ms-MY	
mt-MH	
my-MM	
na-NR	
ne-NP	
nl-NL	

## Show Parts Master

Code Value	Description
no-NO	
oc-FR	
om- ET	
or-IN	
pa-IN	
pl-PL	
ps-PK	
pt-PT	
qu-PE	
rm-CH	
rn-BI	
ro-RO	
ru-RU	
rw-RW	
sa-IN	
sd-PK	
sg-CF	
sh-HR	
si-LK	
sk-SK	
sl-SI	
sm-WS	

## Show Parts Master

Code Value	Description
sn-ZW	
so-SO	
sq-AL	
sr-CS	
ss-ZA	
st-ZA	
su-SD	
sv-SE	
sw-TL	
ta-IN	
te-IN	
tg-TJ	
th-TH	
ti-ET	
tk-TM	
tl-PH	
tn-ZA	
to-TO	
tr-TR	
ts-ZA	
tt-RU	
tw-GH	

## Show Parts Master

Code Value	Description
uk-UA	
ur-PK	
uz-UZ	
vi-VN	
wo-SN	
xh-ZA	
yo-NG	
zh-CN	
zu-ZA	

### ManufacturerPartCode

These field(s) use this type: ManufacturerPartCode.

Manufacturer assigned part code.

Name	ManufacturerPartCode
------	----------------------

\*Base XSD Type: string

### Note

A free form note.

Name	Note
------	------

\*Base XSD Type: string

### PartManufacturerBrand

## Show Parts Master

These field(s) use this type: PartManufacturerBrand,PartManufacturerBrand.

Part Manufacturer Brand

Name	PartManufacturerBrand
------	-----------------------

\*Base XSD Type: string

## PartMasterCountry

These field(s) use this type: PartMasterCountry.

The ISO Country Codelist that the parts master applies.

Name	PartMasterCountry
------	-------------------

\*Base XSD Type: string

Code Value	Description
US	
AF	
AL	
DZ	
AS	
AD	
AO	
AI	
AQ	
AG	
AR	
AM	

## Show Parts Master

---

Code Value	Description
AW	
AU	
AT	
AZ	
BS	
BH	
BD	
BB	
BY	
BE	
BZ	
BJ	
BM	
BT	
BO	
BA	
BW	
BV	
BR	
IO	
BN	
BG	



## Show Parts Master

---

Code Value	Description
BF	
BI	
KH	
CM	
CA	
CV	
KY	
CF	
TD	
CL	
CN	
CX	
CC	
CO	
KM	
CG	
CD	
CK	
CR	
CI	
HR	
CU	

## Show Parts Master

Code Value	Description
CY	
CZ	
DK	
DJ	
DM	
DO	
EC	
EG	
SV	
GQ	
ER	
EE	
ET	
FK	
FO	
FJ	
FI	
FR	
GF	
PF	
TF	
GA	

## Show Parts Master

Code Value	Description
GM	
GE	
DE	
GH	
GI	
GR	
GL	
GD	
GP	
GU	
GT	
GN	
GW	
GY	
HT	
HM	
VA	
HN	
HK	
HU	
IS	
IN	

## Show Parts Master

Code Value	Description
ID	
IR	
IQ	
IE	
IL	
IT	
JM	
JP	
JO	
KZ	
KE	
KI	
KP	
KR	
KW	
KG	
LA	
LV	
LB	
LS	
LR	
LY	

## Show Parts Master

Code Value	Description
LI	
LT	
LU	
MO	
MK	
MG	
MW	
MY	
MV	
ML	
MT	
MH	
MQ	
MR	
MU	
YT	
MX	
FM	
MD	
MC	
MN	
MS	

## Show Parts Master

---

Code Value	Description
MA	
MZ	
MM	
NA	
NR	
NP	
NL	
AN	
NC	
NZ	
NI	
NE	
NG	
NU	
NF	
MP	
NO	
OM	
PK	
PW	
PS	
PA	

## Show Parts Master

---

Code Value	Description
PG	
PY	
PE	
PH	
PN	
PL	
PT	
PR	
QA	
RE	
RO	
RU	
RW	
SH	
KN	
LC	
PM	
VC	
WS	
SM	
ST	
SA	

## Show Parts Master

---

Code Value	Description
SN	
CS	
SC	
SL	
SG	
SK	
SI	
SB	
SO	
ZA	
GS	
ES	
LK	
SD	
SR	
SJ	
SZ	
SE	
CH	
SY	
TW	
TJ	



## Show Parts Master

Code Value	Description
TZ	
TH	
TL	
TG	
TK	
TO	
TT	
TN	
TR	
TM	
TC	
TV	
UG	
UA	
AE	
GB	
UM	
UY	
UZ	
VU	
VE	
VN	

## Show Parts Master

---

Code Value	Description
VG	
VI	
WF	
EH	
YE	
ZM	
ZW	

---

### PartMasterEffectiveDate

These field(s) use this type: **PartMasterEffectiveDate**.

Date on which the parts/prices in this document become effective.

<b>Name</b>	<b>PartMasterEffectiveDate</b>
-------------	--------------------------------

\*Base XSD Type: date

### PartMasterPriceType

These field(s) use this type: **PartMasterPriceType**.

The type of pricing being used (i.e. Retail, Dealer, Warranty, etc).

<b>Name</b>	<b>PartMasterPriceType</b>
-------------	----------------------------

\*Base XSD Type: string

### PartType

These field(s) use this type: **PartType**.

## Show Parts Master

Specifies whether the parts are indicated by manufacturer part code or Part Number - H = Manufacturer Part Code, P = Part Number

Name	PartType
*Base XSD Type: string	
Code Value	Description
H	Manufacturer Part Code
P	"P" = Pending

## PricingCode

These field(s) use this type: **PricingCode**.

Part core code used for pricing.

Name	PricingCode
*Base XSD Type: string	

## Reference

These field(s) use this type: **ReferenceId**.

Reference notation

Name	Reference
*Base XSD Type: string	

## ReferenceNumber

Reference number

Name	ReferenceNumber
*Base XSD Type: string	

## Show Parts Master

---

### SecondaryPassword

These field(s) use this type: SecondaryPassword.

Secondary password used to validate access to the dealer information

Name	SecondaryPassword
------	-------------------

\*Base XSD Type: string

### ShortMfg

These field(s) use this type: SenderNameCode, DestinationNameCode.

Short Manufacturer or RSP Codes

Name	ShortMfg
------	----------

\*Base XSD Type: string

### SupersedingManufacturerPartCode

These field(s) use this type: SupersedingManufacturerPartCode.

Manufacturer assigned part code for superseding part.

Name	SupersedingManufacturerPartCode
------	---------------------------------

\*Base XSD Type: string

### SystemVersion

These field(s) use this type: SystemVersion.

The sender's software version number .

Name	SystemVersion
------	---------------

\*Base XSD Type: string

## Show Parts Master

---

### Text

These field(s) use this type:

**CreatorNameCode,StoreNumber,AreaNumber>Password,DestinationSoftwareCode,DestinationSoftware,StoreNumber,AreaNumber,LogicalId,Component,T**

Indicates generic text type

Name	Text
------	------

\*Base XSD Type: string

### Type

Type

Name	Type
------	------

\*Base XSD Type: string

### UOM

Units of Measure - ea=Each; bx=Box; case=Case; ctn=Carton; gal=Gallon; qt=Quart; pt=Pint; ft=Feet; yd=Yard; in=Inch; L=Liter; m=Meter; cm=Centimeter; kg=Kilograms; g=grams; other=Other

Name	UOM
------	-----

\*Base XSD Type: string

Code Value	Description
ea	Each
bx	Box
case	Case
ctn	Carton
gal	Gallon
qt	Quart

## Show Parts Master

Code Value	Description
pt	Pint
ft	ft = feet
yd	yd = yard
in	in = inch
L	"L" = Canceled
m	m = meter
cm	cm = centimeter
kg	Kilogram
g	Gram
other	
tn	Ton
km	kilometers
mi	miles
hp	horsepower
kw	kilowatt

## URI

These field(s) use this type: **SenderURI, DestinationURI**.

URI

Name	URI
------	-----

Base XSD Type: anyURI

### Fields and Global Attributes

Global declarations are items such as elements, attribute groups, and group definitions. These items are not defined within any particular component. A component may reference these definitions. Within a STAR XML Schemas these are typically known as global fields.

#### ApplicationArea

These field(s) use this type: **ApplicationArea**.

Provides the information that an application may need to know in order to communicate in an integration of two or more business applications. The ApplicationArea is used at the applications layer of communication. While the integration frameworks web services and middleware provide the communication layer that OAGIS operates on top of.

Provides the information that an application may need to know in order to communicate in an integration of two or more business applications. The ApplicationArea is used at the applications layer of communication. While the integration frameworks web services and middleware provide the communication layer that OAGIS operates on top of.

<b>Name</b>	<b>ApplicationArea</b>
<b>Type</b>	<b>ApplicationArea</b>
<b>Nilable</b>	<b>no</b>
<b>Abstract</b>	<b>no</b>

#### XML Instance Representation

```
<ApplicationArea>
  <Sender> Sender </Sender> [1]
  <CreationDateTime> DateTime </CreationDateTime> [1]
  <Signature> Signature </Signature> [0..1]
  <BODId> Code </BODId> [0..1]
  <Destination> Destination </Destination> [1]
</ApplicationArea>
```

#### PartMaster

These field(s) use this type: **PartMaster**.

## Show Parts Master

---

<b>Name</b>	<b>PartMaster</b>
<b>Type</b>	<b>PartMaster</b>
<b>Nilable</b>	<b>no</b>
<b>Abstract</b>	<b>no</b>

### XML Instance Representation

```
<PartMaster>  
  <PartMasterHeader> ... </PartMasterHeader> [1]  
  <PartMasterLine> ... </PartMasterLine> [1..*]  
</PartMaster>
```

### PartMasterHeader

These field(s) use this type: **PartMasterHeader**.

<b>Name</b>	<b>PartMasterHeader</b>
<b>Type</b>	<b>PartMasterHeader</b>
<b>Nilable</b>	<b>no</b>
<b>Abstract</b>	<b>no</b>

### XML Instance Representation

```
<PartMasterHeader>  
  <DocumentDateTime> DocumentDateTime </DocumentDateTime> [0..1]  
  <SecondaryPassword> SecondaryPassword </SecondaryPassword> [0..1]  
  <SecondaryDealerNumber> SecondaryDealerNumber </SecondaryDealerNumber> [0..1]  
  <DocumentId> DocumentId </DocumentId> [0..1]  
  <PartMasterEffectiveDate> PartMasterEffectiveDate </PartMasterEffectiveDate> [1]  
  <PartMasterCountry> PartMasterCountry </PartMasterCountry> [1]  
</PartMasterHeader>
```

### PartMasterLine



## Show Parts Master

These field(s) use this type: **PartMasterLine**.

<b>Name</b>	<b>PartMasterLine</b>
<b>Type</b>	<b>PartMasterLine</b>
<b>Nilable</b>	<b>no</b>
<b>Abstract</b>	<b>no</b>

### XML Instance Representation

```
<PartMasterLine>
  <Part> PartsBase </Part> [1]
  <PartManufacturer> PartManufacturer </PartManufacturer> [0..1]
  <ManufacturerPartCode> ManufacturerPartCode </ManufacturerPartCode> [0..1]
  <PartManufacturerBrand> PartManufacturerBrand </PartManufacturerBrand> [0..1]
  <ItemQuantity> ItemQuantity </ItemQuantity> [0..1]
  <PartMasterPricing> PartMasterPricing </PartMasterPricing> [0..*]
  <PartCoreDetail> PartCoreDetail </PartCoreDetail> [0..*]
  <SupersedingPartGroup> SupersedingPartGroup </SupersedingPartGroup> [0..*]
  <TopSellerGroup> TopSeller </TopSellerGroup> [0..1]
</PartMasterLine>
```

## Show

These field(s) use this type: **Show**.

The Show verb is used when sending the information about a specific instance of a business document or entity. The Show verb may be used to respond to a Get request or it can be used in a publish scenario, where it pushes information to other applications based on a business event. Although BODs based on this verb do not commonly cause updates to occur, there may be times when the component receiving the Show decides to use the information it receives to update. This is entirely the decision of the receiving software component and is not forbidden. The behavior of the Show verb is quite straight forward with one exception. The Show response to any Get request needs to read the request carefully to ensure the response is returning the requested Data Types.

<b>Name</b>	<b>Show</b>
<b>Type</b>	<b>Show</b>
<b>Nilable</b>	<b>no</b>

## Show Parts Master

<b>Abstract</b>	no
-----------------	----

### XML Instance Representation

```
<Show  
confirm="ConfirmType [0..1]">  
  <OriginalBODId> xsd:NMTOKEN </OriginalBODId> [0..1]  
</Show>
```

## ShowPartsMaster

These field(s) use this type: ShowPartsMaster.

<b>Name</b>	ShowPartsMaster
<b>Type</b>	ShowPartsMaster
<b>Nilable</b>	no
<b>Abstract</b>	no

### XML Instance Representation

```
<ShowPartsMaster  
revision="Text [0..1]"  
release="8.1-Lite [0..1]"  
environment="Text [0..1]"  
lang="Language [0..1]"  
bodVersion="Text [0..1]">  
  <ApplicationArea> ... </ApplicationArea> [1]  
  <DataArea> ShowPartsMasterDataArea </DataArea> [1]  
</ShowPartsMaster>
```

## Verb

These field(s) use this type: Verb.

<b>Name</b>	Verb
-------------	------

## Show Parts Master

---

Type	Verb
Nullable	no
Abstract	yes

### XML Instance Representation

```
<Verb/>
```

## Show Parts Master

---